Disclaimer: The following is schema for the GIS feature class Support Structure from Esri ArcFM 10.8.1. Please be advised not all fields are necessarily populated for all records.

Dataset	Name	Alias	Type	Usage	Nullable	Domain	Default Value	Precision	Scale	Length	Editable	Required	Geodatabase Order
ELEC.SupportStructure	OBJECTID		OID		FALSE			10	0	4	FALSE	TRUE	1
ELEC.SupportStructure	CREATIONUSER	Creation User	String		TRUE			0	0	50	TRUE	FALSE	2
ELEC.SupportStructure	DATECREATED	Date Created	Date		TRUE			0	0	8	TRUE	FALSE	3
ELEC.SupportStructure	LASTUSER	Last User	String		TRUE			0	0	50	TRUE	FALSE	4
ELEC.SupportStructure	DATEMODIFIED	Date Modified	Date		TRUE			0	0	8	TRUE	FALSE	5
ELEC.SupportStructure	TAG	Tag	String		TRUE			0	0	15	TRUE	FALSE	6
ELEC.SupportStructure	CONSTRUCTIONSTATUS	Construction Status	Long Integer		TRUE	Construction Status		5	10	0	4	TRUE	FALSE	7
ELEC.SupportStructure	WORKORDERID	Work Order ID	String		TRUE				0	0	20	TRUE	FALSE	8
ELEC.SupportStructure	HYPERLINK	Hyperlink	String		TRUE				0	0	255	TRUE	FALSE	9
ELEC.SupportStructure	SUBTYPECD	Subtype	Long Integer	Subtype	TRUE			70	10	0	4	TRUE	FALSE	10
ELEC.SupportStructure	OWNER	Owner	String		TRUE	Pole Ownership			0	0	32	TRUE	FALSE	11
ELEC.SupportStructure	SYMBOLROTATION	Symbol Rotation	Double		TRUE			0	38	8	8	TRUE	FALSE	12
ELEC.SupportStructure	USAGETYPE	Usage Type	String		TRUE	Pole Use Type			0	0	5	TRUE	FALSE	13
ELEC.SupportStructure	DATESET	Date Set	Date		TRUE				0	0	8	TRUE	FALSE	14
ELEC.SupportStructure	MAINTAINEDBY	Maintained By	String		TRUE	Pole Maintenance			0	0	32	TRUE	FALSE	15
ELEC.SupportStructure	JOINTOWNERDATE	Joint Owner Date	Date		TRUE				0	0	8	TRUE	FALSE	16
ELEC.SupportStructure	PRIVATEPROPERTY	Private Property	String		TRUE	Yes/No Indicator	N		0	0	3	TRUE	FALSE	17
ELEC.SupportStructure	STREETNAME	Street Name	String		TRUE				0	0	46	TRUE	FALSE	18
ELEC.SupportStructure	POLEID	Pole ID	String		TRUE				0	0	16	TRUE	FALSE	19
ELEC.SupportStructure	POLESUBID	Pole Sub ID	String		TRUE				0	0	10	TRUE	FALSE	20
ELEC.SupportStructure	STRUCTUREID	StructureID	String		TRUE				0	0	32	TRUE	FALSE	21
ELEC.SupportStructure	JOINTOWNERCONTRACT	Joint Owner Contract No	String		TRUE				0	0	15	TRUE	FALSE	22
ELEC.SupportStructure	ANIMALPROTECTION	Animal Protection	String		TRUE	Yes/No Indicator	N		0	0	3	TRUE	FALSE	23
ELEC.SupportStructure	INSTALLATIONDATE	Installation Date	Date		TRUE				0	0	8	TRUE	FALSE	24
ELEC.SupportStructure	COMMENTS	Comments	String		TRUE				0	0	255	TRUE	FALSE	25
ELEC.SupportStructure	FIELDNUMBER	Field Number	String		TRUE				0	0	32	TRUE	FALSE	26
ELEC.SupportStructure	DESIGNTYPE	Design Type	Short Integer		TRUE	Design Type			5	0	2	TRUE	FALSE	27
ELEC.SupportStructure	LABELSTRUCTURE	Label Structure	Short Integer		TRUE	Yes/No Domain		0	5	0	2	TRUE	FALSE	28
ELEC.SupportStructure	CENTERLINETAG	Center Line Tag	String		TRUE				0	0	15	TRUE	FALSE	29
ELEC.SupportStructure	QC_LEGACYID	QC Legacy ID	String		TRUE				0	0	20	TRUE	FALSE	30
ELEC.SupportStructure	QC_SOURCEOID	QC Source Object ID	String		TRUE				0	0	200	TRUE	FALSE	31
ELEC.SupportStructure	CROSSSTREETNAME	Cross Street Name	String		TRUE				0	0	255	TRUE	FALSE	32
ELEC.SupportStructure	DIVISION	Division	String		TRUE				0	0	50	TRUE	FALSE	33
ELEC.SupportStructure	REGION	Region	String		TRUE				0	0	50	TRUE	FALSE	34
ELEC.SupportStructure	DISTRICT	District	String		TRUE				0	0	50	TRUE	FALSE	35
ELEC.SupportStructure	AWC	AWC	String		TRUE				0	0	50	TRUE	FALSE	36
ELEC.SupportStructure	ROUTE	Route	String		TRUE				0	0	25	TRUE	FALSE	37
ELEC.SupportStructure	LABELTEXT	Label Text	String		TRUE				0	0	255	TRUE	FALSE	38
ELEC.SupportStructure	LABELTEXT2	Label Text 2	String		TRUE				0	0	255	TRUE	FALSE	39
ELEC.SupportStructure	LABELTEXT3	Label Text 3	String		TRUE				0	0	255	TRUE	FALSE	40
ELEC.SupportStructure	RISER	Riser	String		TRUE	Riser Type			0	0	15	TRUE	FALSE	41
ELEC.SupportStructure	MATERIAL_NUMBER	Material Number	String		TRUE				0	0	50	TRUE	FALSE	42
ELEC.SupportStructure	PRIMARYRISER	Primary Riser	String		TRUE	Yes/No Indicator	N		0	0	3	TRUE	FALSE	43
ELEC.SupportStructure	SECONDARYRISER	Secondary Riser	String		TRUE	Yes/No Indicator	N		0	0	3	TRUE	FALSE	44
ELEC.SupportStructure	STREETSUFFIX	Street Suffix	String		TRUE				0	0	43	TRUE	FALSE	45
ELEC.SupportStructure	OPERATINGCLASS	Operating Class	Short Integer		TRUE	Operating Class			5	0	2	TRUE	FALSE	46
ELEC.SupportStructure	STATE	State	String		TRUE	State			0	0	2	TRUE	FALSE	47
ELEC.SupportStructure	TOWN	Town	String		TRUE	Town Code			0	0	32	TRUE	FALSE	48
ELEC.SupportStructure	QC_HYPERLINK	QC Hyperlink	String		TRUE				0	0	255	TRUE	FALSE	49
ELEC.SupportStructure	OPERATINGCOMPANY	Operating Company	String		TRUE	Operating Company			0	0	4	TRUE	FALSE	50
ELEC.SupportStructure	QC_SYMBOLROTATION	QC Symbol Rotation	Double		TRUE			0	38	8	8	TRUE	FALSE	51
ELEC.SupportStructure	QC_OBJECTID	QC ObjectID	String		TRUE				0	0	50	TRUE	FALSE	52

Dataset	Name	Alias	Type	Usage	Nullable	Domain	Default Value	Precision	Scale	Length	Editable	Required	Geodatabase Order
ELEC.SupportStructure	GLOBALID		Global ID		FALSE			0	0	38	FALSE	TRUE	53
ELEC.SupportStructure	QC_ALTERNATEX	QC Alternate - X	Double		TRUE			38	8	8	TRUE	FALSE	54
ELEC.SupportStructure	QC_ALTERNATEY	QC Alternate - Y	Double		TRUE			38	8	8	TRUE	FALSE	55
ELEC.SupportStructure	QC_ALTERNATEZ	QC Alternate - Z	Double		TRUE			38	8	8	TRUE	FALSE	56
ELEC.SupportStructure	QC_AVNID	QC AVN ID	String		TRUE			0	0	50	TRUE	FALSE	57
ELEC.SupportStructure	SHAPE		Geometry		TRUE			0	0	8	TRUE	TRUE	58